

SpectraPak 1

Name	Description	Is Active	On Device
AutoCal 1	Stack Gas Cals	✓	✓
Opacity Cal	Opacity Cal Request	✓	✓
Flow Cal	Flow Cal Request	✓	✓
Man CG1	Manual Cal Gas 1	✓	✓
Man CG2	Manual Cal Gas 2	✓	✓
Man CG3	Manual Cal Gas 3	✓	✓
Man Purge	Manual Purge	✓	✓
test	test sequence	□	✓

Add
Delete

AutoCal 1

Start Times

Start Time	Is Active
01:00:00	□
09:00:00	✓

Add
Delete

Steps

Step Number	Description	Mask	Set Points	Duration
1	Zero Gas	8	Cal Gas 1, Hands Off Cal, Cal Purge	600
2	High Span Gas	8	Cal Gas 2, Hands Off Cal, Cal Purge	600
3	Low Span Gas	8	Cal Gas 3, Hands Off Cal, Cal Purge	600
4	Purge	8	Purge, Cal Purge	60

Add
Delete
Edit Points

Download
Save

Figure **Error! No text of specified style in document.**-1 Sequences Grid Drill-Down

Sequence Start Times

The *Start Times* grid displays the start times for the event selected in the *Sequences* grid. Multiple starts time are possible. If the “Is Active” is selected the event will run at the listed time. Deselecting the “Is Active” option will prevent the Sequence from running. The Start time could be blank indicating is a manually run operation only. To change the start time click on the number then enter the new time then press save.