

### *Adding Calibration Gas Cylinders*

To add a calibration gas cylinder, perform the following steps.

1. Click on **Add** at the bottom of the pane.
2. A pop-up window will appear titled, *Add a Bottle*. Click on **Next**.
3. The pop-up will switch to the *Bottle Data* view.
4. Enter a **Description** for the bottle.
5. Enter the **Vendor ID** as provided on the *Certificate of Analysis* from the calibration gas vendor.
6. Enter the **Serial Number** as provided on the *Certificate of Analysis* from the calibration gas vendor.
7. Enter the **Certification Date** as provided on the *Certificate of Analysis* from the calibration gas vendor.
8. Enter the **Expiration Date** as provided on the *Certificate of Analysis* from the calibration gas vendor.
9. Click on **Next**.
10. The pop-up will switch to the *Expected Values* view.
11. Click on **Add**.
12. Select the **Gas Type** from the drop down list.
13. Double-click on the **Value** field and enter the calibration gas value.
14. **Engineering Units** are automatically populated with the proper units for the calibration gas.

15. For a blend of multiple types of calibration gases, repeat steps 1 – 14 for each gas type.
16. Once all gas types are added, click on **Finish**.