

Bottle Manager

Other Expected Values

Unit 1 Stack

QA Outputs (3)

Cal Gas 1

[No Bottle]

Cal Gas 2

Expires: 6/2/2025  
Landon Test

Cal Gas 3

Expires: 7/31/2015  
Cal Gas 3

Bottle Inventory (4)

HR Linearity Low

S/N: SDFJKSHD

HR Linearity Mid

S/N: TEST234234

HR Linearity High

S/N: sdfkjsdf

New CG2 Test

S/N: TEST1234

Add

Edit

Retire

Refresh

Unit 1 Stack

Stack Dilution Probe

Unit 1 Outlet

Outlet

Training Room Training 1

### Activating Calibration Gas Cylinders

To activate a calibration gas cylinder, perform the following steps.

1. In the **Bottle Inventory** section, on the desired bottle, left-click and hold the mouse button down.
2. Drag the bottle into the **QA Outputs** section, and release the mouse button.