

SpectraPak 1

Name	Description	Is Active	On Device
AutoCal 1	Stack Gas Cals	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Opacity Cal	Opacity Cal Request	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Flow Cal	Flow Cal Request	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Man CG1	Manual Cal Gas 1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Man CG2	Manual Cal Gas 2	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Man CG3	Manual Cal Gas 3	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Man Purge	Manual Purge	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
test	test sequence	<input type="checkbox"/>	<input checked="" type="checkbox"/>

Add
Delete

AutoCal 1

Start Times

Start Time	Is Active
01:00:00	<input type="checkbox"/>
09:00:00	<input checked="" type="checkbox"/>

Add
Delete

Steps

Step Number	Description	Mask	Set Points	Duration
1	Zero Gas	8	Cal Gas 1, Hands Off Cal, Cal Purge	600
2	High Span Gas	8	Cal Gas 2, Hands Off Cal, Cal Purge	600
3	Low Span Gas	8	Cal Gas 3, Hands Off Cal, Cal Purge	600
4	Purge	8	Purge, Cal Purge	60

Add
Delete
Edit Points

Download
Save

Figure **Error! No text of specified style in document.**-1 Sequences Grid Drill-Down

Sequence Steps

Each of the *Sequence Steps* has a duration, listed in seconds, for the relevant operation. When a *Sequence Step* is completed the next *Sequence Step* listed will trigger and run for the duration listed. Clicking on the *Sequence Step* allows the end-user to edit the point that is used. To change the duration click on the number then enter the new duration in seconds then press save.