

SpectraPak 1

Name	Description	Is Active	On Device
AutoCal 1	Stack Gas Cals	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Opacity Cal	Opacity Cal Request	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Flow Cal	Flow Cal Request	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Man CG1	Manual Cal Gas 1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Man CG2	Manual Cal Gas 2	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Man CG3	Manual Cal Gas 3	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Man Purge	Manual Purge	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
test	test sequence	<input type="checkbox"/>	<input checked="" type="checkbox"/>

Add Delete

AutoCal 1

Start Times

Start Time	Is Active
01:00:00	<input type="checkbox"/>
09:00:00	<input checked="" type="checkbox"/>

Add Delete

Steps

Step Number	Description	Mask	Set Points	Duration
1	Zero Gas	8	Cal Gas 1, Hands Off Cal, Cal Purge	600
2	High Span Gas	8	Cal Gas 2, Hands Off Cal, Cal Purge	600
3	Low Span Gas	8	Cal Gas 3, Hands Off Cal, Cal Purge	600
4	Purge	8	Purge, Cal Purge	60

Add Delete Edit Points

Download Save

Figure **Error! No text of specified style in document.**-1 Sequences Grid Drill-Down

Download Sequences

Once created, the *Sequences* must be downloaded to the *SpectraPak®-E*. Perform the following steps to download the *Sequences*.

1. Select the **Sequences Sub-Tab**.
2. Click the **Download** button. The button will disable and fade and change to **Downloading**. Once the operation is completed, the button will enable and change back to **Download**.