

Bottle Manager

Other Expected Values

Unit 1 Stack

QA Outputs (3)

Cal Gas 1

[No Bottle]

Cal Gas 2

Expires: 6/2/2025
Landon Test

Cal Gas 3

Expires: 7/31/2015
Cal Gas 3

Bottle Inventory (4)

HR Linearity Low

S/N: SDFLKJSHD

HR Linearity Mid

S/N: TEST234234

HR Linearity High

S/N: sdfkjsdf

New CG2 Test

S/N: TEST1234

Add

Edit

Retire

Refresh

Unit 1 Stack

Stack Dilution Probe

Unit 1 Outlet

Outlet

Training Room Training 1

Editing Calibration Gas Cylinders

To edit a calibration gas cylinder, perform the following steps.

1. Select the desired calibration gas cylinder.
2. Click on **Edit** at the bottom of the pane.
3. A pop-up window will appear titled, *Edit an Active Bottle*. Click on **Next**.
4. The pop-up will switch to the *Bottle Data* view.
5. Update the information, as required. Click on **Next**.
6. The pop-up will switch to the *Expected Values* view.
7. Update the information, as required.
8. Click on **Finish**.